

PEACH BUSINESS SOFTWARE



POS DOCKET DRIVER & OPEN DRAWER COMMANDS

On the computer that has the POS Docket machine installed, create 2 new Generic Text printers. (Check what port it is using, but usually it is LPT1) Do not set as default and do a test print to make sure all works correctly first.

Call one of the Generic text drivers '**Opendrawer**' and the other '**Docket**'.

Next we need to setup a page layout.

Goto: *Printers & Faxes > File > Server Properties*




Click on the 'Create New Form' option; then type in the form name: 'POS' And fill in the paper size as shown at the bottom.

Save the form in the top right before you exit.

Then right click on the 'Docket' printer and go to properties.

When the properties screen opens, jump to the 'Device Settings' tab and make the following changes. By default the settings are set to 'Letter', just drop down the box and select 'POS'.






ands' Tab:

Type these codes here:

BEGIN PRINT JOB:
<1B><70><30><7D><7D>

END PRINT JOB:
<1D><56><42><7D>




When you click on the 'Apply' Button, the codes will change to these. Click on 'OK' and exit.

In Peach make sure you have the following settings:
Database & Options > Options > Setup Options > POS tab.

The 'CASH DRAWER CODES' that are represented by 'xxxxx' can be replaced with one of the codes on the right.

This part is trial and error as different codes pop different models of cash draws. Enter one of the codes, then close down the setup options screen and restart Peach to test with an invoice reprint. Keep following these steps until one of the codes pops the drawer.

Please note: Setup Printers in Peach will need the docket printer only attached to the 'POS' option.



The screenshot shows a configuration window with the following fields and options:

- Receipt Docket
- Print Receipt Heading
- Receipt A4 Size
- Use Printer Driver for Docket
- Receipt Salesman
- Freight Includes GST
- POS Bold/Norm: 0 0
- POS Red/Black: 0 0
- Cash Drawer Codes: xxxxxxxxxx
- Cut Sheet Codes: [empty]
- Drawer/Printer Font: api
- POS Init String: [empty]
- POS Copies: 1
- Dkt Feed Lines Offset: [empty]

- Choose one that works:**
- 027112048
 - 027112000250250
 - 027112048125125
 - 027112000050100
 - 007
 - 027

Once everything is working correctly on the computer that the Docket Printer is attached to, you may share the docket and opendrawer printers and allow other machines to print to them too.

Simply repeat the steps on Page 1 on each machine you share to. The rest of the steps on the other pages will be saved.



If you have any questions during any part of this process, please call Peach Support on (02) 9630 - 2999